

## How to Update W10M Build using Upgrade SPKG/CAB (With PC)



### Requirements

- ❖ A PC running Windows Operating System (W7SP1 or later)
- ❖ Windows 10 Mobile Device

**THIS GUIDE IS THE “INSTALLATION PART” OF THE “UPGRADE COLLECTION” GUIDES !**

“How to Backup Upgrade Cabs for each W10M Build” Guide



W10M Group



Mega.nz

Windows 10 Mobile (Lumia) Group :- <https://t.me/Windows10Phone>



## Preparations

---


> Download iutool and Install it in your PC



W10M Group



Mega.nz



### Notice

There are a lot of iutool versions out there, but some are quite old.

With old iutool versions, when installing newer build cabs like 1703, the Update will fail to start.

So, I recommend you use the above provided version always.




## Steps

---

> Open Command prompt in Administrator mode.

> Then copy paste this command in there

**Cd C:\Program Files (x86)\Windows Kits\10\Tools\bin\i386**



```
Administrator: Command Prompt
Microsoft Windows [Version 10.0.22000.120]
(c) Microsoft Corporation. All rights reserved.

C:\WINDOWS\system32>cd C:\Program Files (x86)\Windows Kits\10\Tools\bin\i386
C:\Program Files (x86)\Windows Kits\10\Tools\bin\i386>
```

If the CMD returns an error saying can't find the specified path, then make sure ;

1. Open File explorer and go to "**C:\Program Files (x86)\Windows Kits\10\Tools\bin\i386**" and check if the files are present in that i386 folder
2. Check if your PC is running 64 bit Windows, if it's 32 bit, the command should be ;

**Cd C:\Program Files\Windows Kits\10\Tools\bin\i386**

> Now we will proceed with Installing cabs, before that read the below note carefully ;


If you got the cabs by following another resource rather than Group Guide, then ;

- Make sure the cabs you have are for your phone Model exactly.
- Make sure the cabs are not Mixed (means make sure the cabs included are only for one specific update and for one specific update)  
Auto Filtering and Installing is not done in iutool directly, that's why I'm checking it.
- Make sure the cabs are not damaged/corrupted.

If you followed Group Upgrade cab collection Guide to the letter, you don't have to worry about above issues.



- > Now go to the folder where the cabs you want to install are placed.
- > Copy the path to the folder ;



“example Screenshot”

- > Now back to the CMD
- > The command to push the Upgrade CAB/SPKG files are ;

**iutool -v -p “PathToTheUpgradeCabFolder”**

(Replace ‘PathToTheUpgradeCabFolder’ with the Folder path for your cab files)

Example :- iutool -v -p “C:\Users\lasit\Desktop\L1520\10.0.10586.107”

- > If you placed the path correctly, then it will start pushing the cabs and will start the update once all cabs are pushed to device

```
Administrator: Command Prompt - iutool -v -p "C:\Users\lasit\Desktop\L1520\10.0.10586"
Microsoft Windows [Version 10.0.22000.120]
(c) Microsoft Corporation. All rights reserved.

C:\WINDOWS\system32>cd C:\Program Files (x86)\Windows Kits\10\Tools\bin\i386
C:\Program Files (x86)\Windows Kits\10\Tools\bin\i386>iutool -v -p "C:\Users\lasit\Desktop\L1520\10.0.10586"
(IUTool Version: 13:54:04/Apr 29 2015)

Log file: C:\Users\lasit\AppData\Local\Temp\IUTool-{299338D7-E9AD-4D02-BD74-B341894FDEEF}.etl

[1] Started device f69026181c51787b4b48eeabb12a7052
[1] Transferring files started
[1] Transferring files complete: 144 files
[1] Update started
```

- > Do the same procedure with other updates you have collected.



## Known Error Codes

---

- ❖ You can refer to official Microsoft Docs for all the error codes ;

[IUTool error codes - Windows 10 hardware dev | Microsoft Docs](https://docs.microsoft.com/en-us/windows-hardware/drivers/iutool/iutool-error-codes)

## Additional Notes

---

- This Guide is the “Installation Part” of the “Upgrade File Collection” Guides
- The IUTool version used in here supports every W10M Build upgrade files
- W10M 1511 Upgrade uses SPKG files but all above builds use CAB files  
But the install Command is same for both types.
- When updating the phone, Push the update cabs to this order

**10.0.10586 → 10.0.14393 → 10.0.15063 → 10.0.15254**

### BUT :

You can skip Updating to **15063** when you are in **14393**, you can instead push **15254 Upgrade Cabs** to jump from 14393 to 15254 directly.

- You can't downgrade the OS version by pushing older update cab files

## Credits

---

- ✓ Thx Microsoft for IUTool

Thank You !



\_\_\_\_ ***Lasitha Samarasinghe*** \_\_\_\_

